



Set Up and Run WRF

Wei Wang
NCAR/ESSL/MMM




WRF System Flowchart




Outline

- Running WRF code
 - Before you run..
 - Running **real-data** case
- Basic runtime options for a single domain run (*namelist*)
- Check output
- Simple trouble shooting



Before You Run ..

- Check and make sure appropriate executables are created in **WRFV3/main/** directory:
 - `ideal.exe`
 - `real.exe`
 - `wrf.exe`
 - `ndown.exe`
- If you are running a real-data case, be sure that files from WPS are correctly generated:
 - `met_em.d01.*`, for ARW
- Prepare `namelist.input` for runtime options.



WRF test case directories

You have these choices in **WRFV3/test/**

(made at compile time):

`em_real`

} 3d real-data

`em_quarter_ss`

`em_b_wave`

`em_les`

`em_heldsuarez`

} 3d ideal

`em_hill2d_x`


`em_squall2d_x`

`em_squall2d_y`

`em_grav2d_x`

} 2d ideal

`em_seabreeze2d_x`




Steps to Run

1. cd to *run/* or one of the *test case* directories
2. Link or copy WPS output files to the directory for real-data cases
3. Edit *namelist.input* file for the appropriate grid and times of the case
4. Run initialization program (*real.exe*)
5. Run model executable, *wrf.exe*




Running Real-Data Case



Running Real-Data Case


- If you have compiled the *em_real* case, you should have:
 - real.exe* - real data initialization program
 - wrf.exe* - model executable
 - ndown.exe* - program for doing one-way nesting
 - These executables are linked to:
 - WRFV3/run**and
 - WRFV3/test/*em_real***
- ➔ One can go to either directory to run.



WRFV3/test/em_ *real* directory

LANDUSE.TBL -> ../../run/LANDUSE.TBL
ETAMPNEW_DATA -> ../../run/ETAMPNEW_DATA
GENPARAM.TBL -> ../../run/GENPARAM.TBL
RRTM_DATA -> ../../run/RRTM_DATA
SOILPARAM.TBL -> ../../run/SOILPARAM.TBL
VEGPARAM.TBL -> ../../run/VEGPARAM.TBL
urban_param.tbl -> ../../run/urban_param.tbl
tr49t67 -> ../../run/tr49t67
tr49t85 -> ../../run/tr49t85
tr67t85 -> ../../run/tr67t85
gribmap.txt -> ../../run/gribmap.txt
grib2map.tbl -> ../../run/grib2map.tbl
namelist.input - require editing
real.exe -> ../../main/real.exe
wrf.exe -> ../../main/wrf.exe
ndown.exe -> ../../main/ndown.exe

.... (a few more)




Running WRF Real-data Cases

- One must successfully run WPS, and create `met_em.*` file for more than one time period
- Link or copy WPS output files to the run directory:


```
cd test/em_real
```

```
ln -s ../ ../WPS/met_em.* .
```



Running WRF Real-data Cases

- Edit `namelist.input` file for runtime options (at minimum, one must edit `&time_control` for start, end and integration times, and `&domains` for grid dimensions)
- Run the real-data initialization program:
 - `./real.exe`, if compiled serially / SMP, or
 - `mpirun -np N ./real.exe`, for a MPI jobwhere N is the number of processors requested



Running WRF Real-data Cases

- Successfully running this program will create model initial and boundary files:

wrfinput_d01

wrfbdy_d01

*Single time level
data at model's
start time*

*Multiple time level data
at the lateral boundary,
and only for domain 1*



Running WRF Real-data Cases

- Run the model executable by typing:

```
./wrf.exe >& wrf.out &
```

or

```
mpirun -np N ./wrf.exe &
```

- Successfully running the model will create model *history* file:


```
wrfout_d01_2005-08-28_00:00:00
```

And *restart* file if selected:

```
wrfirst_d01_<date>
```




Basic namelist Options



What is a namelist?

- A Fortran namelist contains a list of *runtime* options for the code to read in during its execution.
- Use of a namelist allows one to change runtime configuration without the need to recompile the source code.




&time_control

```
run_days           = 0,  
run_hours          = 24,  
run_minutes        = 0,  
run_seconds        = 0,  
start_year         = 2000, 2000, 2000,  
start_month        = 01, 01, 01,  
start_day          = 24, 24, 24,  
start_hour         = 12, 12, 12,  
start_minute       = 00, 00, 00,  
start_second       = 00, 00, 00,  
end_year           = 2000, 2000, 2000,  
end_month          = 01, 01, 01,  
end_day            = 25, 25, 25,  
end_hour           = 12, 12, 12,  
end_minute         = 00, 00, 00,  
end_second         = 00, 00, 00,  
interval_seconds   = 21600  
history_interval   = 180, 60, 60  
frame_per_outfile  = 1000, 1000, 1000,  
restart_interval   = 360,
```


First column: domain 1 option

nest options



Notes on `&time_control`

- `run_*` time variables:
 - Model simulation length: `wrf.exe` and domain 1 only
- `start_*` and `end_*` time variables:
 - Program `real` will use WPS output between these times to produce lateral (and lower) boundary file
 - They can also be used to specify the start and end of simulation times for the coarse grid.



Notes on `&time_control`

- *Interval_seconds*:
 - Time interval between WPS output times, and LBC update frequency
- *history_interval*:
 - Time interval in minutes when a history output time is written
 - The time stamp in a history file name is the time when the history file is first written, and multiple time periods may be written in one file. e.g. a history file for domain 1 that is first written for 1200 UTC Jan 24 2000 is

`wrfout_d01_2000-01-24_12:00:00`



Notes on `&time_control`

- *frame_per_outfile*:
 - Number of history times written to one file.
- *restart_interval*:
 - Time interval in minutes when a restart file is written.
 - By default, restart file is not written at hour 0.
 - A restart file contains only one time level data, and its valid time is in its file name, e.g. a restart file for domain 1 that is valid for 0000 UTC Jan 25 2000 is

`wrfrst_d01_2000-01-25_00:00:00`




&time_control

```
io_form_history      = 2,  
io_form_restart     = 2,  
io_form_input       = 2,  
io_form_boundary    = 2,  
debug_level         = 0,
```

IO format options:



- = 1, binary
- = 2, netcdf (most common)
- = 4, PHDF5
- = 5, Grib 1
- =10, Grib 2

Debug print control:
Increasing values give
more prints.



&domains

```
time_step                = 180
time_step_fract_num      = 0,
time_step_fract_den      = 1,
max_dom                  = 1,
s_we                     = 1, 1, 1,
e_we                     = 74, 112, 94,
s_sn                     = 1, 1, 1,
e_sn                     = 61, 97, 91,
s_vert                   = 1, 1, 1,
e_vert                   = 28, 28, 28,
num_metgrid_levels       = 21
dx                       = 30000, 10000, 3333,
dy                       = 30000, 10000, 3333,
eta_levels                = 1.0, 0.996, 0.99, 0.98, ... 0.0
p_top_requested          = 5000,
```




Notes on `&domains`

- *time_step, time_step_fract_num, time_step_fract_den*:
 - Time step for model integration in seconds.
 - Fractional time step specified in separate integers of numerator and denominator.
 - ARW: $6 \times DX$ (DX is grid distance in km)
- *s_we, s_sn, s_vert*:
 - Starting indices in X, Y, and Z direction; 1 for domain 1.
- *e_we, e_sn, e_vert*:
 - Model grid dimensions in X, Y and Z directions.
- *num_metgrid_levels*:
 - Number of *metgrid* (input) data levels.
- *dx, dy*:
 - grid distances in meters for ARW




Notes on `&domains`

- *p_top_requested*:
 - Pressure value at the model top.
 - Constrained by the available data from WPS.
- *eta_levels*:
 - Specify your own model levels from 1.0 to 0.0.
 - If not specified, program *real* will calculate a set of levels for you




Where do I start?

- Always start with a *namelist* template provided in a test case directory, whether it is an ideal case, or real-data case.
 - A number of namelist templates are provided in *test/em_real/* directory
- Use document to guide the modification of the namelist values:
 - run/README.namelist
 - User's Guide, Chapter 5
 - Full list of namelist can be found in Registry files: Registry.EM, and registry.io_boilerplate




To run a job in a different directory..

- Directories *run/* and *test_<case>/* are convenient places to run, but it does not have to be.
- Copy or link the content of these directories to another directory, including physics data files, wrf input and boundary files and wrf **namelist** and **executables**, and you should be able to run a job anywhere on your system.




Check Output



Output After a Model Run

- Standard out/error files:
`wrf.out`, or `rs1.*` files
- Model history file(s):
`wrfout_d01_<date>`
- Model restart file(s), optional
`wrfirst_d01_<date>`



Output from a multi-processor run

The standard out and error will go to the following files for a MPI run:

```
mpirun -np 4 .wrf.exe →
```

```
rsl.out.0000
```

```
rsl.error.0000
```

```
rsl.out.0001
```

```
rsl.error.0001
```


```
rsl.out.0002
```

```
rsl.error.0002
```

```
rsl.out.0003
```

```
rsl.error.0003
```

There is one pair of files for each processor requested



What to Look for in a standard out File?


Check run log file by typing

```
tail wrf.out, or
```

```
tail rsl.out.0000
```

You should see the following if the job is successfully completed:

```
wrf: SUCCESS COMPLETE WRF
```



How to Check Model History File?

- Use **ncdump**:


```
ncdump -v Times wrfout_d01_<date>
```

to check output times. Or

```
ncdump -v U wrfout_d01_<date>
```

to check a particular variable (U)

- Use **ncview** or **ncBrowse** (great tools!)
- Use post-processing tools (see talks later)



What is in a *wrf.out* or *rsl* file?

- Time taken to compute one model step:

```
Timing for main: time 2000-01-24_12:03:00 on domain 1: 3.25000 elapsed seconds.  
Timing for main: time 2000-01-24_12:06:00 on domain 1: 1.50000 elapsed seconds.  
Timing for main: time 2000-01-24_12:09:00 on domain 1: 1.50000 elapsed seconds.  
Timing for main: time 2000-01-24_12:12:00 on domain 1: 1.55000 elapsed seconds.
```


- Time taken to write history and restart file:

```
Timing for Writing wrfout_d01_2000-01-24_18:00:00 for domain 1: 0.14000 elapsed  
seconds.
```


- Any model error prints:

```
5 points exceeded cfl=2 in domain 1 at time 4.200000 MAX AT i,j,k: 123 48 3  
cfl,w,d(eta)= 4.165821
```

→ An indication the model has become numerically unstable



Simple Trouble Shooting




Often-seen runtime problems

- `module_configure: initial_config: error reading
namelist: &dynamics`

→ Typos or erroneous namelist variable exist in
namelist record &dynamics in *namelist.input*
file


- `input_wrf.F: SIZE MISMATCH: namelist
ide,jde,num_metgrid_levels= 70 61 27 ; input
data ide,jde,num_metgrid_levels= 74 61 27`

→ Grid dimensions in error



Often-seen runtime problems

- `Segmentation fault` (core dumped)
- Often typing 'unlimit' or equivalent can help when this happens quickly in a run.
- 121 points `exceeded cfl=2` in domain 1 at time 4.200000 MAX AT i,j,k: 123 48 3 cfl,w,d(eta)= 4.165821
- Model becomes unstable due to various reasons. If it happens soon after the start time, check input data, and/or reduce time step.



References

- Information on compiling and running WRF, and a more extensive list of namelist options and their definition / explanations can be found in the [User's Guide, Chapter 5](#)
- Also see '[Nesting Setup and Run](#)' talk.

http://www.mmm.ucar.edu/wrf/users/tutorial/tutorial_presentation.htm

